# **COMANDOS AGI - ASTERISK.**

## **ANSWER**

ANSWER Usaqe:

Asserts answer.

Answers channel if not already in answer state. RETURNS:

-1 on channel failure

0 if successful

## CHANNEL STATUS

CHANNEL STATUS [<channelname>]

Returns the status of the specified or connected channel. If no channel name is given it returns the status of the current

channel.

**RETURNS:** 

O Channel is down and available 1 Channel is down, but reserved 2 Channel is off hook

3 Digits (or equivalent) have been dialed

4 Line is ringing

5 Remote end is ringing

6 Line is up

7 Line is busy

## DATABASE DEL

Usage: DATABASE DEL <family> <key>

Removes database key/value.

Deletes an entry in the Asterisk database for a given family and

key.

**RETURNS:** 

1 if successful 0 otherwise

## DATABASE DELTREE

DATABASE DELTREE <family> [keytree]

Removes database keytree/value.

Deletes a family or specific keytree within a family in the

Asterisk database.

**RETURNS:** 

1 if successful

0 otherwise

## DATABASE GET

DATABASE GET <family> <key>

Gets database value.

Retrieves an entry in the Asterisk database for a given family and

key.

**RETURNS:** 

0 if <key> is not set

1 if <key> is set and returns the variable in parenthesis

example return code: 200 result=1 (testvariable)

## DATABASE PUT

DATABASE PUT <family> <key> <value>

Adds/updates database value.

Adds or updates an entry in the Asterisk database for a given

family, key, and value.

**RETURNS:** 

1 if successful 0 otherwise

#### **EXEC**

Usage: EXEC <application> <options>

Executes a given application.

Executes <application> with given <options>.

**RETURNS:** 

Whatever the application returns successfully

-2 on failure to find application

## **GET DATA**

GET DATA <file to be streamed> [timeout] [max digits] Usage:

Gets data on a channel.

Stream the given file, and receive DTMF data.

the channel at the other end.

**RETURNS:** 

Digits received from the channel at the other end.

## **GET VARIABLE**

GET VARIABLE <variablename> Usaqe:

Gets a channel variable.

**RETURNS:** 

0 if <variablename> is not set

1 if <variablename> is set and returns the variable in

parenthesis

example return code: 200 result=1 (testvariable)

## **HANGUP**

Usage: HANGUP [<channelname>]

Hangs up the current or specified channel.

If no channel name is given, hangs up the current channel

RETURNS: 1 on success -1 on failure

# NOOP

Usage: NOOP

Does nothing.

RETURNS:
0 - always

#### RECEIVE CHAR

Usage: RECEIVE CHAR <timeout>

Receives text from channels supporting it.

Receives a character of text on a channel. Specify timeout to be

the maximum

time to wait for input in milliseconds, or 0 for infinite. Most

channels do

not support the reception of text.

**RETURNS:** 

ASCII numerical value of the character if one is received

0 if the channel does not support text reception

-1 only on error/hangup.

# RECORD FILE

Usage: RECORD FILE <filename> <format>

<escape digits> <timeout> [offset samples] [BEEP]

[s=silence]

Records to a given file.

Record to a file until a given DTMF digit in the sequence is received.

recerved.

The format will specify what kind of file will be recorded. The

timeout is the

maximum record time in milliseconds, or -1 for no timeout. "offset

samples" is

optional, and if provided will seek to the offset without exceeding

the end of

the file. "silence" is the number of seconds of silence allowed

before the

function returns despite the lack of DTMF digits or reaching

timeout. The

"silence" value must be preceded by "s=" and is optional.

RETURNS:

-1 on hangup or error

## SAY DIGITS

Usage: SAY DIGITS <number> <escape digits>

Say a given digit string, returning early if any of the given DTMF digits are

received on the channel.

**RETURNS:** 

0 if playback completes without a digit being pressed ASCII numerical value of the digit if one was pressed -1 on error/hangup

#### SAY NUMBER

Usage: SAY NUMBER <number> <escape digits>

Say a given number, returning early if any of the given DTMF digits

are

received on the channel.

RETURNS:

O if playback completes without a digit being pressed ASCII numerical value of the digit if one was pressed -1 on error/hangup

## SAY PHONETIC

Usage: SAY PHONETIC <string> <escape digits>

Say a given character string with phonetics, returning early if any

of the

given DTMF digits are received on the channel.

**RETURNS:** 

O if playback completes without a digit being pressed ASCII numerical value of the digit if one was pressed -1 on error/hangup

#### SAY TIME

Usage: SAY TIME <time> <escape digits>

Say a given time, returning early if any of the given DTMF digits are received

on the channel. <time> is the number of seconds elapsed since 00:00:00

January 1, 1970, Coordinated Universal Time (UTC).

RETURNS:

O if playback completes without a digit being pressed ASCII numerical value of the digit if one was pressed -1 on error/hangup

## SEND IMAGE

Usage: SEND IMAGE <image>

Sends the given image on a channel.

Most channels do not support the transmission of images. Image names should not

include extensions.

**RETURNS:** 

0 if image is sent or if the channel does not support image

transmission

-1 only on error/hangup

## SEND TEXT

Usage: SEND TEXT "<text to send>"

Sends the given text on a channel.

Most channels do not support the transmission of text. Text

consisting of

greater than one word should be placed in quotes since the command

only

accepts a single argument.

RETURNS:

O if text is sent, or if the channel does not support text

transmission

-1 only on error/hangup

## SET AUTOHANGUP

Usage: SET AUTOHANGUP <time>

Autohangup channel in some time.

Cause the channel to automatically hangup at <time> seconds in the future. Of course it can be hungup before then as well. Setting to

0 will

cause the autohangup feature to be disabled on this channel.

RETURNS: 0 - always

# SET CALLERID

Usage: SET CALLERID < number>

Changes the callerid of the current channel.

RETURNS: 1 - always

## SET CONTEXT

Usage: SET CONTEXT <desired context>

Sets the context for continuation upon exiting the application.

RETURNS: 0 - always

# SET EXTENSION

Usage: SET EXTENSION < new extension>

Changes the extension for continuation upon exiting the

application.

RETURNS: 0 - always

# SET MUSIC

Usage: SET MUSIC ON <on off> <class>

Enables/Disables the music on hold generator. If <class> is not

specified then the default music on hold class will be used.  ${\tt RETURNS:}$ 

0 - always

# SET PRIORITY

Usage: SET PRIORITY < num>

Changes the priority for continuation upon exiting the application.

RETURNS: 0 - always

## SET VARIABLE

Usage: SET VARIABLE <variablename> <value>

Sets a channel variable.

RETURNS: 1 - always

## STREAM FILE

Usage: STREAM FILE <filename> <escape digits> [sample offset]

Sends audio file on channel.

Send the given file, allowing playback to be interrupted by the given digits,

if any. Use double quotes for the digits if you wish none to be permitted. If

sample offset is provided then the audio will seek to sample offset before play

starts. Remember, the file extension must not be included in the filename.

**RETURNS:** 

O if playback completes without a digit being pressed ASCII numerical value of the digit if one was pressed

-1 on error or if the channel was disconnected

## TDD MODE

Usage: TDD MODE <on off>

Enable/Disable TDD transmission/reception on a channel.

RETURNS:

1 if successful

0 if channel is not TDD-capable

#### **VERBOSE**

Usage: VERBOSE <message> <level>

Logs a message to the asterisk verbose log.

Sends <message> to the console via verbose message system.

<level> is the the verbose level (1-4)

RETURNS: 1 - always

# WAIT FOR DIGIT

WAIT FOR DIGIT <timeout> Usage:

Waits for a digit to be pressed. Waits up to 'timeout' milliseconds for channel to receive a DTMF  $\,$ 

digit.

Use -1 for the timeout value if you desire the call to block

indefinitely.

**RETURNS:** 

ASCII numerical value of the digit if one is received

-1 on channel failure 0 if no digit is received in the timeout